Alogent Comp Guide

Remote Deposit

12/17/2013
Profit Stars
Suzanne Sturm

Table of Contents

I. **Overview** – Target Audience/Purpose of Application
II. **Color Palette** – high level definition of each color to be used in the application
III. **Typography** – all the different text styles (i.e. heading, sub heading, etc.)
IV. **Controls** – all the different control styles (i.e. each type of button, pull downs, checkboxes, etc.)
V. **Screen Flow** – the order in which each screen is presented to the user
VI. **Layout/Spacing** – the specific layout and structure of each screen
VII. **Form Elements** – for each UI screen, sets which elements should use which styles
VIII. **Iconography** – the icons and animations to be used
IX. **Keyboard Behavior/Navigation** – how users can navigate through the UI using the keyboard

I. Overview

Remote Deposit is an application now being offered on the web where customers can easily deposit money to multiple business accounts by scanning checks through ProfitStars cutting edge technology.

Our customers include...

The application is designed to fit in a computers screen resolution of 1024 x 768 pixels.
It is compatible in Internet Explorer 8, 9 and 10 as well as FireFox.

The application allows our clients to customize the interface to fit their branding needs which will be addressed later in this document.

II. Color Palette





These two colors constitute the gradient from top to bottom that make up the nave bar at the top of the application and the primary buttons.



Nav Bar



Primary Buttons



#0088CC

This color is the sub-navigation for links you find throughout the application



Sub-Nav Tabs



#2C5070


This is the color for Main Headings that uses the color grey below for its background.



Heading with Background

#CCCCCC

This grey color is also used for default buttons, box shadows and the overall background of the application.



The color red is used to denote alerts or a strong call to action as well as denoting errors that may occur.

#d80a0a





Alerts

III. Typography

Font-Family: Segoe UI

Default Content Size: 14px

Heading: 21px




Heading with Background

#2C5070

Heading Color

Sub-Heading: 16px Bold Black **#000000**



Link: 16px Bold

#0088CC

Link Color



Sub-Link: 12px Bold



Active Link: 16px Bold

#555555

Active Link Color



IV. Controls

Buttons



These buttons are used for main functions in the UI such as logging in or updating the application. They are used sparingly usually when only one choice is present and important.
Specs:

border: 1px solid #999999;
border-radius: 6px;
box-shadow: 0 1px rgba(255, 255, 255, 0.15), 0 2px 2px rgba(0, 0, 0, 0.15) inset;
cursor: pointer;
font-size: 15px;
font-weight: bold;
height: 30px;
min-width: 100px;



The rest of the buttons are smaller with the primary call to action (blue) button always on the left. The secondary or default buttons are always grey and to the right of the primary.
Specs:


border: 1px solid #999999;
border-radius: 6px;
box-shadow: 0 1px rgba(255, 255, 255, 0.15), 0 2px 2px rgba(0, 0, 0, 0.15) inset;
cursor: pointer;
font-size: 12px;
font-weight: bold;
height: 20px;
min-width: 100px;



The only exception is the logout button with the only difference it being red.


Check Boxes

Check boxes are used on the Deposit page to pick which items should be remembered from the payer. There is an option to select all at the top. Items can be removed by checking the box and clicking on the "Remove Items" button.



Input Boxes

Input boxes can be modified on the Deposit page under "Item Details" if an item did not scan correctly. These items can be edited and saved or removed altogether.



Account Selection




Click on the arrow to the right to select an account. Subject to change…

V. Screen Flow


1. Log In




2. Update




3. If a deposit is already in progress you must cancel it to do a new one




4. Select Account



5. Input Expected Total



6. Submit Deposit



VI. Layout/Spacing

The web page has a navigation bar with content boxes that hold components. The boxes have a light grey border with a box shadow around the bottom right.





Figure 1 Page Layout

Each component is rounded by 6 pixels and has a grey border that is #CCCCCC and 1px wide

All elements on the page have fixed spacing or padding of 10 pixels around each object and from the edge of the div or box in which it is contained.

The width and the height of the page is fixed to fill the display at 1024 x 768 resolution without any vertical or horizontal scroll bars. The page will not re-size if the resolution is increased (or decreased) or the browser window is expanded (or reduced).

VII. Form Elements



Currently the only form elements in this application are input fields. These fields have a box shadow with a height of 26px. The labels have a font-size of 14px and a font-weight of 600.

Specs:

font-size: 12px;
border: 1px solid #CCC;
border-radius: 5px;
box-shadow: 0 1px rgba(255, 255, 255, 0.15), 0 2px 2px rgba(0, 0, 0, 0.15) inset;
text-align: right;
height: 26px;
padding: 0 5px;

VIII. Iconography

 This image animates when a user first logs in to indicate that a user's credentials are being checked to make sure they have rights to access the database. It is also present when updating the application on the Accounts page.

 This image rotates while checks are being scanned on the deposit page.

 This image indicates canceling an edit when a user is adjusting the total in the transaction items dialogue box in the upper left hand corner of the Deposit page.

 This image indicates editing an item when a user is adjusting the total in the transaction items dialogue box in the upper left hand corner of the Deposit page.

 This is the current icon for selecting an account.

 These arrows allow the user to view the last item added to deposit if there transaction got interrupted and they need to continue with that transaction or cancel it to start a new one.

 These icons allow the user to expand and collapse the details of their accounts in the accounts list such as the account number, etc.

140 icons are also available in the Bootstrap library available in dark gray (default) and white.

icon-exclamation-sign	icon-gift	icon-leaf	icon-fire
icon-eye-open	icon-eye-close	icon-warning-sign	icon-plane
icon-calendar	icon-random	icon-comment	icon-magnet
icon-chevron-up	icon-chevron-down	icon-retweet	icon-shopping-cart
icon-folder-close	icon-folder-open	icon-resize-vertical	icon-resize-horizontal
icon-hdd	icon-bullhorn	icon-bell	icon-certificate
icon-thumbs-up	icon-thumbs-down	icon-hand-right	icon-hand-left
icon-hand-up	icon-hand-down	icon-circle-arrow-right	icon-circle-arrow-left
icon-circle-arrow-up	icon-circle-arrow-down	icon-globe	icon-wrench
icon-tasks	icon-filter	icon-briefcase	icon-fullscreen

icon-glass	icon-music	icon-search	icon-envelope
icon-heart	icon-star	icon-star-empty	icon-user
icon-film	icon-th-large	icon-th	icon-th-list
icon-ok	icon-remove	icon-zoom-in	icon-zoom-out
icon-off	icon-signal	icon-cog	icon-trash
icon-home	icon-file	icon-time	icon-road
icon-download-alt	icon-download	icon-upload	icon-inbox
icon-play-circle	icon-repeat	icon-refresh	icon-list-alt
icon-lock	icon-flag	icon-headphones	icon-volume-off
icon-volume-down	icon-volume-up	icon-qrcode	icon-barcode
icon-tag	icon-tags	icon-book	icon-bookmark
icon-print	icon-camera	icon-font	icon-bold
icon-italic	icon-text-height	icon-text-width	icon-align-left
icon-align-center	icon-align-right	icon-align-justify	icon-list
icon-indent-left	icon-indent-right	icon-facetime-video	icon-picture
icon-pencil	icon-map-marker	icon-adjust	icon-tint
icon-edit	icon-share	icon-check	icon-move
icon-step-backward	icon-fast-backward	icon-backward	icon-play
icon-pause	icon-stop	icon-forward	icon-fast-forward
icon-step-forward	icon-eject	icon-chevron-left	icon-chevron-right
icon-plus-sign	icon-minus-sign	icon-remove-sign	icon-ok-sign
icon-question-sign	icon-info-sign	icon-screenshot	icon-remove-circle
icon-ok-circle	icon-ban-circle	icon-arrow-left	icon-arrow-right
icon-arrow-up	icon-arrow-down	icon-share-alt	icon-resize-full
icon-resize-small	icon-plus	icon-minus	icon-asterisk

Presently, we are using the icon-warning-sign for errors in red

IX. Keyboard Behavior/Navigation

1. Basic Navigation and Address Bar

alt+home	Go to Home webpage.
alt+arrow right / alt+arrow left	Go to next / previous webpage.
alt+d or f6	Jump to address bar. f6 additionally navigates through window elements.
ctrl+enter	Complete a .com address in address bar: adds "http://" prefix and a ".com"-suffix, then loads the webpage.
ctrl+shift+enter	Complete an URI in address bar with user-defined suffix: adds "http://" prefix and suffix (e.g. .net, .org, .de, ...), then loads the webpage. Set the suffix in tools:options (alt+t, then o), languages (alt+l), and enter to suffix field at bottom.
alt+arrow down or f4	Open webpages visited in the past when in address bar. Includes Favorites and History. Navigate with arrow keys and enter to visit.
delete or shift+delete	Delete past visited webpages from address bar history (also see shortcut above).

2. Tabbed Browsing main

ctrl+t	Open new tab in same window.
ctrl+k	Duplicate current tab.
ctrl+tab / ctrl+shift+tab	Jump to next / jump to previous browser tab.
ctrl+w	Close the current tab.
ctrl+shift+t	Restore closed tab (open previously closed tab).
ctrl+q	Show Tabs: Open or close quick tab view.
ctrl+shift+q	Show Tabs: Open list of tabs. Then use arrow keys and enter to select or escape to exit.
ctrl+1 ... ctrl+9	Jump to browser tab 1 - 9.
On Link: ctrl+ left mouse button	Open link in new background tab (sometimes link is opened in new window; as an alternative, use right mouse button and press w).
alt+enter	Open typed webpage address in new background tab.

3. Navigate Webpages in IE8

arrow down / arrow up	Scroll down / scroll up inside a webpage.
page up / page down	Jump one page down / jump one page up (space / shift+space works as well).
home / end	Move to the beginning or end of a document.
ctrl++ / ctrl+-	Increase text size / decrease text size (zoom in and out).

ctrl+0	Reset text size to default (zoom to 100%).
tab / shift+tab	Move forward / move backwards through items on a webpage. Press and hold tab button to skip through multiple links.
shift+f10	When on link: Display a context menu for a link.
enter	Activate a selected link.
tab / shift+tab, and enter or space	In web forms: move forward / move backwards through form items. Press space to activate action buttons, select boxes, or radio buttons.
ctrl+a	Select all content on webpage.
f5 or ctrl+r	Refresh the current webpage.
ctrl+f5	Refresh the current webpage with cache override.
f7	Turn caret browsing on or off (movable cursor on page).
esc	Stop loading webpage.

4. Favorites, History and Search

ctrl+i	Open Favorites box.
ctrl+shift+i	Open Favorites box in pinned mode.
ctrl+h	Open History box.
ctrl+shift+h	Open History in pinned mode.
ctrl+j	Open Feeds.
ctrl+shift+j	Open Feeds in pinned mode.
ctrl+ left mouse click	In the History or Favorites boxes, open link as background tab.
ctrl+d	Add the current webpage to favorites.
ctrl+b	Open the Organize Favorites dialog box. Use tab to navigate and alt and shift+alt to move items up or down in list.
ctrl+f or f3	Open find window. Press escape to exit.

5. main for Privacy Settings

ctrl+shift+f	Turn in-private filtering on or off (watch icon change in status bar)
ctrl+shift+p	Open private browsing window / incognito mode.
ctrl+shift+delete	Open 'Delete Browsing History' Menu.

6. Manage IE8 Windows

alt+space	Opens the title bar menu.
alt+space+enter	Restore Window (default Windows feature).
alt+space+x	Maximize Window (default Windows feature).
alt+space+n	Minimize Window (default Windows feature).

alt+shift+enter	Toggle regular window / full screen without toolbars
f11	Turn full page view on or off (default Windows feature).
f6	Move forward between window elements.
ctrl+n	Open a new browser window.
f4	Close IE8 Window.

7. Instant Search

ctrl+e	Jump to the Instant Search box (box on top right corner of browser window).
ctrl+arrow down	View list of search providers.
alt+enter	Open search results in new tab.

8. The Rest

alt+p	Print the current webpage.
f12	Open Developer Tools.
ctrl+o or ctrl+l	Open location.
alt+v+c	View webpage source in default editor (used to be ctrl+u but that was discontinued).
f1	Display Internet Explorer Help or to display context Help about an item in a dialog box.